

DUMPSQUEEN

NCSS 2G RA OaM 2.2

Nokia NCS 20022101010

Version Demo

Total Demo Questions: 10

Total Premium Questions: 118

Buy Premium PDF

<https://dumpsqueen.com>

support@dumpsqueen.com

dumpsqueen.com

QUESTION NO: 1

What is indicated to a mobile station, if in a GPRS system information message the USF granularity is set to '1'?

- A. MS will transmit on the next uplink block following the appearance of the USF.
- B. MS will transmit on the next four uplink blocks following the appearance of the USF.
- C. MS will transmit on the next uplink block following the appearance of the TFI.
- D. MS will transmit on the next four uplink blocks following the appearance of the TFI.

ANSWER: B

QUESTION NO: 2

Which functional unit in Flexi BSC is used for packet abis over TDM?

- A. ETPT.
- B. BCSU.
- C. ETPE.
- D. ETPA.

ANSWER: A

QUESTION NO: 3

Nethawk is used on which interface to check sync loss problems on PCU?

- A. A interface.
- B. Abis Interface.
- C. GB Interface.
- D. Ater Interface.

ANSWER: B

QUESTION NO: 4

How many BTS resets are possible in a Flexi Multiradio BTS GSM/EDGE?

- A.** BCF (site) reset: resets all modules/units in the site except transmission submodules (Flxx).BTS (sector) reset: resets a single BTS object, including all TRXs that are part of the BTS object configuration.System Module reset.
- B.** BCF (site) reset: resets all modules/units in the site except transmission submodules (Flxx).BTS (sector) reset: resets a single BTS object, including all TRXs that are part of the BTS object configuration.TRX reset: resets all configured TRX.OMU reset is not supported at all.System Module reset.
- C.** BCF (site) reset: resets all modules/units in the site except transmission submodules (Flxx).BTS (sector) reset: resets a single BTS object, including all TRXs that are part of the BTS object configuration.TRX reset: resets a single TRX.OMU reset: OMU is restarted.System Module reset.
- D.** BCF (site) reset: resets all modules/units in the site except transmission submodules (Flxx).BTS (sector) reset: resets a single BTS object, including all TRXs that are part of the BTS object configuration.TRX reset: resets a single TRX.OMU reset is not supported at all.System Module reset.

ANSWER: D

QUESTION NO: 5

Where are the MML commands that are fired daily stored?

- A.** BLCODE.
- B.** SCMANA.
- C.** LFILES.
- D.** MMDIRE.

ANSWER: D

QUESTION NO: 6

Under normal circumstances why should the GPRS mobile reachable timer never expire?

- A.** Because the periodic cell update would be performed before it expires.
- B.** Because the periodic LA update would be performed before it expires.
- C.** Because the periodic data would be sent before it expires.
- D.** Because the periodic RA update would be performed before it expires.

ANSWER: D

QUESTION NO: 7

How many maximum number of PCUs are in pool?

- A. 42.
- B. 52.
- C. 50.
- D. 64.

ANSWER: C

QUESTION NO: 8

Priority package is published in NOLS for:

- A. selected customers.
- B. all customers.
- C. no such software is published.
- D. new feature availability.

ANSWER: A

QUESTION NO: 9

Which Network operation mode is in use, if only GSM control channels are used for GPRS operation?

- A. NOM IV.
- B. NOM III.
- C. NOM II.
- D. NOM I.

ANSWER: C

QUESTION NO: 10

The result of A8 algorithm is?

- A. SRES.
- B. Kc.
- C. RAND.
- D. Ki.

ANSWER: B